


7-5-5 OSPF 繞路設定 (一)



★ OSPF 繞路規劃

◆ 自治系統網路(一)_介面設定(pkt)



Router	Network_1	Network_2	Network_3	Area
R1	192.168.0.0/24	192.168.100.0/24		Area 0
R2	192.168.100.0/24	192.168.1.0/24	192.168.101.0/24	Area 0
R3	192.168.101.0/24	192.168.2.0/24	192.168.102.0/24	Area 0
R4	192.168.102.0/24	192.168.3.0/24	202.168.1.0/24	Area 0
R_R5	120.118.166.0/24	202.168.1.0/24		Area 0



7-5-5 OSPF 繞路設定 (二)



★ OSPF 繞路設定

◆ R1 設定

R1(config)#**ip routing** [啟動 IP routing 功能]

R1(config)#**route ospf 1** [設定 OSPF 功能, process-id = 1]

R1(config-router)#**network 192.168.0.0 0.0.0.255 area 0** [設定網路範圍與區域]

R1(config-router)#**network 192.168.100.0 0.0.0.255 area 0**

R1(config)#**do show ip route** [顯示路由表]

Gateway of last resort is not set

C 192.168.0.0/24 is directly connected, FastEthernet1/0

C 192.168.100.0/24 is directly connected, FastEthernet0/1

★ 繞路測試

◆ 自治系統網路(一)_OSPF 設定.pkg

◆ R1 測試

C:\>ping 192.168.1.1 [OK]

C:\>ping 192.168.2.1 [OK]

C:\>ping 192.168.3.1 [OK]

C:\>ping 120.118.166.1 [OK]

