


8-2-5 VLAN 附加 DHCP 設定(一)



★ 網路環境規劃

- ◆ 沿用『單交換機_VLAN 設定+繞路』
- ◆ 修改主機環境



8-2-5 VLAN 附加 DHCP 設定(二)



✿ 路由器 R1 規劃

```
R1(config)#ip dhcp excluded-address 192.168.1.250 192.168.1.251
R1(config)#ip dhcp excluded-address 192.168.2.250 192.168.2.251
R1(config)#ip dhcp pool vlan10
R1(dhcp-config)#network 192.168.1.0 255.255.255.0
R1(dhcp-config)#default-route 192.168.1.254
R1(dhcp-config)#dns-server 168.95.1.1
R1(dhcp-config)#exit
R1(config)#ip dhcp pool vlan20
R1(dhcp-config)#network 192.168.2.0 255.255.255.0
R1(dhcp-config)#default-router 192.168.2.254
R1(dhcp-config)#dns-server 168.95.1.1
R1(dhcp-config)#end
```

✿ DHCP 測試

◆ PC1

```
C:\>ipconfig /release
IP Address.....: 0.0.0.0
Subnet Mask.....: 0.0.0.0
Default Gateway.: 0.0.0.0
DNS Server.....: 0.0.0.0

C:\>ipconfig /renew
IP Address.....: 192.168.1.1
Subnet Mask.....: 255.255.255.0
Default Gateway.: 192.168.1.254
DNS Server.....: 168.95.1.1
```

